

Social Booth Settings - Filters

Modified on: Sun, 12 Jul, 2015 at 6:23 AM

1 Enable Filters

2 Standard Filters

Color	<input checked="" type="checkbox"/>	B&W	<input checked="" type="checkbox"/>	Sepia	<input checked="" type="checkbox"/>
Vintage 1	<input checked="" type="checkbox"/>	Vintage 2	<input checked="" type="checkbox"/>	Vintage 3	<input checked="" type="checkbox"/>

3 Advanced Filters

Cartoon	<input type="checkbox"/>	Sketch	<input type="checkbox"/>	Cross Process	<input type="checkbox"/>						
Thermo	<input type="checkbox"/>	Night Vision	<input type="checkbox"/>	Comic Book	<input type="checkbox"/>						
Pixel Art	<input type="checkbox"/>	Size	12	Mosaic	<input type="checkbox"/>	Size	16	Lite Brite	<input type="checkbox"/>	Size	12
Warhol	<input type="checkbox"/>	Dave Hill	<input type="checkbox"/>								

4 Only allow 1 Filter to be printed per session

Enable user selection of Filters. Max 6 allowed.
WARNING Advanced filters are much slower than Standard filters and require more processing time. Use sparingly, especially with multi-shot templates.
Only allowing 1 filter to be printed per session will prevent users from going back and forth printing multiple versions.

(<http://imgur.com/s6nxQHe>)

- 1. Enable Filters**
Enable Filters to let the user select a filter for their shots. The filters will be applied after the session is done and the user will be shown a preview of their shots with the actual filter applied
- 2. Select Filters**
By turning off certain filters, you can limit the filters the user has to select from
- 3. Advanced Filters**

Add an advanced filter to your photo. Advanced filters are much slower than traditional filters are will require additional processing time.

4. **Only Allow Filter to be printed per Session**

Checking this option will make sure users can't go back and forth to the Filter Selection screen to select new filters to print. Once they print 1 filter, they can select another filter to upload, but not to print.

*Note: To have the user select the filter **before** the session has started, use the Layout Selection feature in the "Display" Tab. For example, create an event setting with only Color Filter enabled, and another with only B&W Filter enabled. Then Make your Layout Selection screen so the user can select Color or B&W.*